- 1. Install Samba
- Update package lists:

Bash

```
sudo apt update
```

• Install Samba:

Bash

```
sudo apt install samba samba-common-bin
```

- 2. Configure Samba
- Edit the Samba configuration file:

Bash

```
sudo nano /etc/samba/smb.conf
```

- Make necessary changes:
 - [global] section:
 - workgroup = WORKGROUP (Replace with your desired workgroup name)
 - security = user
 - encrypt passwords = yes
 - passdb backend = tdbsam
 - Create a share (example: "my_share"):

```
[my_share]
path = /path/to/your/share/directory
public = yes
writable = yes
guest ok = yes
read only = no
create mask = 0664
directory mask = 0775
```

- Replace /path/to/your/share/directory with the actual path to the directory you want to share.
- Adjust permissions (create mask, directory mask) according to your needs.

 Save and close the smb.conf file. 3. Create Samba User Accounts • Create a new user (optional): Bash sudo adduser <username> Set Samba password for the user: Bash sudo smbpasswd -a <username> 4. Restart Samba • Restart the Samba service: Bash sudo systemctl restart smbd Bash sudo systemctl restart nmbd 5. Test the Samba Share On a Windows machine: Open File Explorer. • In the address bar, type \\<server_name> (replace <server_name> with the hostname or IP address of your Linux server). • You should see the shared folder ("my_share" in this example). • Try to access and modify files within the shared folder. 6. Troubleshooting Check Samba logs:

Bash

```
sudo tail -f /var/log/samba/log.smbd
```

• Use smbclient to test connectivity:

Bash

smbclient //<server_name>/my_share -U <username>